## Lecture Nº1.7. OS definition. Main OS

**Operating system** is the master software program that controls the allocation and usage of all internal resources (e.g., memory, queuing, input/output, central processing unit [CPU], time, disk space, and transmission and reception processes) and, thereby, enables and controls the operation of the entire computer system. The OS forms the foundation for application software that performs end-user tasks such as word processing and mathematical calculation. An OS is largely software, although there are firmware components.

*Firmware* is Software programs that are stored in a computer's read-only memory (ROM), where they are available for instantaneous use. Firmware is hard-coded and stored on a silicon chip and, therefore, is not affected by loss of electrical power, hence the term firm.

**Software** is the programs and routines for a computer system. System software includes programs and routines required to run the computer. Application software includes programs that enable users to perform tasks that use computer resources.

### 1.7.1. BIOS

**BIOS** stands for Basic Input and Output System. It is sometimes called ROM BIOS because it is stored in a Read-Only Memory (ROM) chip on the mainboard. BIOS is the first program to run when you turn on your computer.

BIOS performs the following functions:

1. Initializing and testing hardware in your computer (a process called "*POST*", for Power On Self Test).

2. Loading and running your operating system.

3. Helping your operating system and application programs to manage your PC hardware by means of a set of routines called **BIOS Run-Time Service**.

#### 1.7.1.1. BIOS SETUP

**BIOS Setup** is an interactive BIOS program that you need to run when:

1. Changing the hardware of your system. (for example: installing a new Hard Disk etc..)

2. Modifying the behavior of your computer. (for example: changing the system time or date, or turning special features on or off etc.)

3. Enhancing your computer's behavior. (for example: speeding up performance by turning on shadowing or cache) How to run BIOS Setup:

• To access BIOS setup menu, press **<DEL>** key after "POST", and before the OS is loaded. The BIOS usually display the following message:

#### Press DEL to enter SETUP

#### 1.7.1.2. CMOS

**CMOS** is the memory maintained by a battery.

The BIOS uses CMOS to store the settings you have selected in SETUP. The CMOS also maintains the internal clock. Every time you turn on your computer, the BIOS Looks into CMOS for the settings you have selected and configures your computer accordingly. If the battery is out of power, the CMOS data will be lost and POST will issue a "CMOS invalid" or "CMOS checksum invalid" message. If this happens, you have to replace the battery and do some proper settings in SETUP.

#### 1.7.1.3. POST

**POST** is an acronym for Power On Self Test.

POST will that all things the BIOS does before the operating system is started. Each of POST routines is assigned a POST code, a unique number which is sent to I/O port 080h before the routine is executed.

#### 1.7.1.4. STANDARD CMOS FEATURES (fig. 1.7.1.)

**Standard CMOS Setup** records some basic system hardware configuration and sets the system clock and error handling. You only need to modify the configuration values of this option if you want to change your system hardware configuration or when the data stored in the CMOS memory gets lost or damaged.

<F6>: Load all options with the BIOS default values.

<F7>: Load all options with the Setup default values.

#### 1.7.1.5. ADVANCED BIOS FEATURES

**ADVANCED BIOS FEATURES** improves your system performance or sets up system features according to your preference (fig. 1.7.2.).

#### CMOS Setup Utility - Copyright (C) 1984-2001 Award Software Standard CMOS Features

Date (mm:dd:yy)	Tue, Oct 24 1999	Item Help
Time (hh:mm:ss)	9:52:15	Menu Level 🛛 🕨
<ul> <li>IDE Primary Master</li> <li>IDE Primary Slave</li> <li>IDE Secondary Master</li> <li>IDE Secondary Slave</li> </ul>	Press Enter 13022 MB Press Enter None Press Enter None Press Enter None	
Drive A Drive B	1.44M, 3.5 in. None	
Video Halt On	EGA/VGA All Errors	
Base Memory Extended Memory Total Memory	640K 31744K 32768K	

↑↓→←:Move Enter:Select +/-/PU/PD:Value F10:Save ESC:Exit F1:General Help F5:Previous Values F6:Fail-Safe Defaults F7:Optimized Defaults

#### Fig. 1.7.1. Standard CMOS Features

Virus Warning	Disabled	Item Help
CPU Internal Cache	Enabled	Menu Level
External Cache	Enabled	
CPU L2 Cache ECC Checking	Enabled	
Quick Power On Self Test	Enabled	
First Boot Device	Floppy	
Second Boot Device	HDD-0	
Third Boot Device	CDROM	
Boot Other Device	Enabled	
Swap Floppy Drive	Disabled	
Boot Up Floppy Seek	Disabled	
Boot Up NumLock Status	On	
Gate A20 Option	Fast	
Typematic Rate Setting	Disabled	
×Typematic Rate (Chars/Sec)	6	
×Typematic Delay (Msec)	250	
Security Option	Setup	
OS Select For DRAM > 64MB	Non-OS2	
Video BIOS Shadow	Enabled	
C8000-CBFFF Shadow	Disabled	
CC000-CFFFF Shadow	Disabled	
D0000-D3FFF Shadow	Disabled	
D4000-D7FFF Shadow	Disabled	
D8000-DBFFF Shadow	Disabled	
DC000-DFFFF Shadow	Disabled	

#### CMOS Setup Utility - Copyright (C) 1984-2001 Award Software Advanced BIOS Features

t→→←:Move Enter:Select +/-/PU/PD:Value F10:Save ESC:Exit F1:General Help F5:Previous Values F6:Fail-Safe Defaults F7:Optimized Defaults

#### Fig. 1.7.2. Advanced BIOS Features

CMOS Setup Utility - Copyright (C) 1984-2001 Award Software Advanced Chipset Features

T.			
	DRAM Timing By SPD	Enabled	Item Help
	×DRAM Clock	100MHZ	Menu Level
	×SDRAM Cycle Length	3	
	×Bank Interleave	Disabled	
	DRAM Drive Strength	Auto	
	×DRAM Drive Value	2F	
	Memory Hole	Disabled	
	PCI Master Pipeline Req	Enabled	
	P2C/C2P Concurrency	Enabled	
	Fast R-W Turn Around	Disabled	
	System BIOS Cacheable	Disabled	
	Video RAM Cacheable	Disabled	
	AGP Aperture Size	64M	
	AGP 4X Mode	Enabled	
	AGP Driving Control	Auto	
	×AGP Driving Value	DA	
	AGP Fast Write	Disabled	
	OnChip USB	Enabled	
	OnChip USB 2	Enabled	
	USB Keyboard Support	Disabled	
	OnChip Sound	Auto	
	CPU to PCI Write Buffer	Enabled	
	PCI Dynamic Bursting	Disabled	
	PCI Master 0 WS Write	Enabled	
	PCI Delay Transaction	Enabled	
	PCI#2 Access #1 Retry	Enabled	
	AGP Master 1 WS Write	Disabled	
	AGP Master 1 WS Read	Disabled	

1.7.1.6. ADVANCED CHIPSET FEATURES ADVANCED CHIPSET FEATURES is used to modify the values of chipset registers. These registers control the system options (Fig. 1.7.3.).

↑↓→←:Move Enter:Select +/-/PU/PD:Value F10:Save ESC:Exit F1:General Help F5:Previous Values F6:Fail-Safe Defaults F7:Optimized Defaults

Fig. 1.7.3. Advanced Chipset Features

Int	egrated Peripherals	Jost Award Soltware
Int OnChip IDE Channel 0 OnChip IDE Channel 1 IDE Prefetch Mode Primary Master PIO Primary Slave PIO Secondary Master PIO Secondary Slave PIO	egrated Peripherals Enabled Enabled Auto Auto Auto Auto	Item Help Menu Level →
Primary Master UDMA Primary Slave UDMA Secondary Master UDMA Secondary Slave UDMA Init Display First IDE HDD Block Mode Onboard FDD Controller Onboard Serial Port 1 Onboard Serial Port 2 UART 2 Mode IR Function Duplex X TX, RX inverting enable Onboard Parallel Port Onboard Parallel Port Onboard Parallel Mode Parallel Port EPP Type Onboard Legacy Audio Sound Blaster SB I/O Base Address SB IRO Select	Auto Auto Auto PCI Slot Enabled Enabled Auto Standard Half No, Yes 378/IRQ7 Normal 3 EPP1.9 Enabled Disabled 220H IRO 5	
SB DMA Select MPU-401 MPU-401 I/O Address Game Port (200-207H)	DMA 1 Disabled 330-333H Enabled	

CMOS Satur Htility Convright (C) 1094 2001 Award Softward

1.7.1.7. INTEGRATED PERIPHERALS INTEGRATED PERIPHERALS option allows you to get some information inside your system when it is working (Fig. 1.7.4.).

↑↓→←:Move Enter:Select +/-/PU/PD:Value F10:Save ESC:Exit F1:General Help F5:Previous Values F6:Fail-Safe Defaults F7:Optimized Defaults

#### Fig. 1.7.4. Integrated Peripherals

## **1.7.8. POWER MANAGEMENT SETUP POWER MANAGEMENT SETUP** allows you to set the system's power saving functions (Fig. 1.7.5.).

CMOS Setup Utility - Copyright (C) 1984-2001 Award Software Power Management Setup

ACPI Function	Enabled	Item Help
Power Management	Press Enter	Menu Level 🕨
ACPI Suspend Type	S1(POS)	102 generative and an an an an an and an
PM Control by APM	Yes	
Video Off Option	Suspend -> Off	
Video Off Method	V/H SYNC+Blank	
MODEM Use IRQ	3	
Soft-Off by PWRBTN	Instant-Off	
State After Power Failure	Auto	
Wake Up Events	Press Enter	

↑↓→←:Move Enter:Select +/-/PU/PD:Value F10:Save ESC:Exit F1:General Help F5:Previous Values F6:Fail-Safe Defaults F7:Optimized Defaults

#### Fig. 1.7.5. Power Management Setup

#### Press **<Enter>** on the Power Management item, then there appears a list of options for you to configure further setting (Fig. 1.7.6.).

CMOS Setup Utility - Copyright (C) 1984-2001 Award Software Power Management

Power Man	agement	User Define			Item Hel	р
HDD Power	Down	Disable		Ν	1enu Level	•
Doze Mode		Disable				
Suspend M	ode	Disable				
t↓→←:Move	Enter: Select	+/-/PU/PD:Value	F10:Save	ESC:Exit	F1:General	Help

F5:Previous Values F6:Fail-Safe Defaults F7:Optimized Defaults Fig. 1.7.6. Power Management

#### 1.7.1.9. PNP / PCI CONFIGURATION PNP/PCI CONFIGURATION allows you to modify the system's power saving functions (Fig. 1.7.7.).

CMOS Setup Utility - Copyright (C) 1984-2001 Award Software PnP/PCI Configurations

PNP OS Installed	No	Item Help
Reset Configuration Data	Disabled	Menu Level 🔸
Resources Controlled By ×IRQ Resources ×DMA Resources	Auto(ESCD) Press Enter Press Enter	
PCI/VGA Palette Snoop Assign IRQ For VGA Assign IRQ For USB PCI SLOT 1/5 IRQ Assigned PCI SLOT 2/6 IRQ Assigned PCI SLOT 3 IRQ Assigned PCI SLOT 4 IRQ Assigned	Disabled Enabled Auto Auto Auto Auto Auto	

↑↓→←:Move Enter:Select +/-/PU/PD:Value F10:Save ESC:Exit F1:General Help F5:Previous Values F6:Fail-Safe Defaults F7:Optimized Defaults Fig. 1.7.7. PNP/PCI Configurations

#### 1.7.1.10. SMARTDOC ANTI-BURN SHIELD

This section (Fig. 1.7.8.) helps to get more information about your system including CPU temperature, FAN speed and voltage. It is recommended that you contact your mainboard supplier to get proper values about the setting of the CPU temperature.

CMOS Setup Utility - Copyright (C) 1984-2001 Award Software SmartDoc Anti-Burn Shield

CPU Warning Temperature	Disabled	Item Help
Shutdown For Temperature	Disabled	Menu Level 🕠
Shutdown For CPUEan	Disabled	
Current CPU Temp	36°C/96°E	
Current System Temp.	°C/32°F	
Current CPUFAN1 Speed	5120 RPM	
Current CPUFAN2 Speed	0 RPM	
Vcore	1.53V	
VDD	3.34V	
3.3V	3.28V	
5V	5.00V	
12V	11.76V	

↑↓→←:Move Enter:Select +/-/PU/PD:Value F10:Save ESC:Exit F1:General Help F5:Previous Values F6:Fail-Safe Defaults F7:Optimized Defaults

#### Fig. 1.7.8. Smartdoc Anti-Burn Shield

# 1.7.1.11. FREQUENCY/VOLTAGE CONTROL (Fig. 1.7.9.)

CMOS Setup Utility - Copyright (C) 1984-2001 Award Software Frequency Control

Redstorm Overclocking Tech	Press Enter	Item Help
Auto Detect DIMM/PCI Clk Spread Spectrum Modulated CPU Host/PCI Clock CPU Voltage Regulator	Enabled Disabled Default Default	Menu Level 🕨

↑↓→←:Move Enter:Select +/-/PU/PD:Value F10:Save ESC:Exit F1:General Help F5:Previous Values F6:Fail-Safe Defaults F7:Optimized Defaults Fig. 1.7.9. Frequency Control

#### 1.7.2. Operating system MS-DOS. System programs.

System programs name programs which supervise over processes inside of a computer. These programs provide communication of a computer with the devices connected to them and an environment.

System programs DOS is contained in two latent files – IO.SYS and MSDOS.SYS or IBMBIO.COM and IBMDOS.COM.

The first file (IO.SYS or IBMBIO.COM) contains the dilator BIOS, the program which supervises over internal processes in a computer. In the certain maintenance it establishes communication between separate components of a computer.

The second file MSDOS.SYS or IBMDOS.COM provides an exchange with standard system devices of a personal computer. This file puts at system disposal programmer a number of additional procedures which allow to use base functions of a personal computer and to not write each time for this purpose

#### 1.7.2.1. The interpreter of commands

After computer inclusion and loading of files IO.SYS and MSDOS.SYS a computer still not in a condition to perceive commands from the user. Not in a condition to contact a computer in "natural" language. For an establishment of such contact the so-called interpreter of commands which contains in a file COMMAND.COM serves. It provides understanding with a personal computer of commands of the user and their performance.

All commands, that we submit to a personal computer in operating system MS-DOS, represent reduction of English terms, for example, abbreviation COMP answers English Compare, etc. Commands which move the user to operating system, are perceived by a file COMMAND.COM, are checked on conformity to language rules (syntax), and are interpreted. Only after loading a file COMMAND.COM the personal computer can perceive commands and understand the user.

#### 1.7.2.2. Data and files

The major concepts in MS-DOS are files and catalogues (directories).

Files

Data in a computer are kept in files. Data in files can be kept in any form. In the form of files on a disk addresses of clientele or texts are kept both service and applied programs, and data obtained by programs means.

MS-DOS allows to carry out following operations with files • Creation,

- •Defense,
- Change,
- •The analysis or processing.

Files have names without which information search is practically impossible or it demands very much greater expenses of time.

#### Files names and their expansions

- The file name can consist of a whole no more than of 12 symbols. These 12 symbols are distributed inside of a file name thus:
- File name a maximum of 9 avmbala
- File name a maximum of 8 symbols,
- Expansion of a file name a maximum 3 symbols,
- Both these parts are separated from each other by a point which represents 12-th symbol.
- Thus, as well as a dividing point, and expansions of a file name can be absent absolutely.
- The further restrictions consist that in a file name and its expansion is authorized to use not all symbols. It is authorized to apply only following letters to a file name, figures and symbols: A-Z 0-9 \$ and #'() - %!

Letters can be used both lower case, and capital – they are perceived MS-DOS as equivalent. Lower case letters at introduction automatically turn in capital.

It is impossible to use following symbols which are reserved for special functions in a name and expansion:

?.;: = \* / \ + " |

The colon separates the disk drive designation, and the point separates in a file name of a name from expansion.

MS-DOS perceives also longer files names but as the name can consist only of 8 symbols, обрезает them after 8-th symbol.

Expansion of files names are not necessary components. However they are used by many programs for a designation and recognition of file type.

#### The file specification

Before a file name you can put the disk drive name and the catalogue name. It is necessary in case the caused file is on the disk drive which is not at present active.

If files which are on a disk, are carried under catalogues after a designation of a disk before a file name you can specify a name of the corresponding catalogue. In this case MS-DOS carries out search of a file in the specified catalogue of the disk drive.

The full description of a file which includes the store and a directory in which it is located name the file specification.

#### The reserved files names

Except for restriction on quantity of symbols in a file name, there is a restriction on use of those names which are reserved MS-DOS for the needs. These names MS-DOS uses, carrying out operations of input and output through peripheral devices. If you use the reserved names as names for the files, you will address not to the file, and to corresponding peripheral device. In MS-DOS following files names are reserved.

Name	Purpose	
AUX	The asynchronous interface	
CLOCK \$	The hours driver	
COM1	The first consecutive interface	
COM2	The second consecutive interface	
COM3	The third consecutive interface	
COM4	The fourth consecutive interface	
CON	The console (the keyboard and the display)	
LPT1	The first parallel interface	
LPT2	The second parallel interface	
LPT3	The third parallel interface	
NUL	Absent output	
PRN	The printer	

#### Symbols of substitution in files names

In most cases the command processes one file. There can be a necessity by means of one command to process some the same files. In this case you can process them separately by introduction of the same commands for each file which will demand greater expenses of time. But in MS-DOS there is an opportunity to address at once to all files of one kind by means of one command. For this purpose it is necessary to enter only a conterminous part of files group names. For parts of files names which differ, it is enough to you to use special symbols which are stipulated for this purpose in MS-DOS and refer to as symbols of substitution.

Special symbols of substitution which carry out function of a place designation in a file name, refer to as masks. Such masks is ? and \*. These symbols cannot be used in names of separate files.

? – replaces in a file name or its expansion only one letter. In a file name it is possible to use some question marks.

? – it is possible to use in any place of a file name and its expansion. It replaces any symbol which meets in names of different files on this place.

Unlike it \* it is possible to use for replacement of several symbols. It can be applied to replacement both one, and all symbols of a file name and its expansion. Since that position in which the asterisk is entered, it replaces all symbols which have remained.

#### 1.7.2.3. Kinds of commands

In MS-DOS there are two commands groups:

- Internal
- External

**Internal commands**, for example, VER and SET, are processed and carried out by the interpreter of commands which is located in a file COMMAND.COM. This file at start of a computer is loaded together with MS-DOS and remains in computer operative memory.

*External commands* are carried out by small service programs (utilities) which for performance should be loaded from files on a diskette or a hard disk into operative memory.

The general format of a command:

**Square brackets** [] – contain components (keywords, parameters and variables) any command which can be included in a command structure at will of the user, at desire they can be lowered. If such fragment all the same joins in a command square brackets in a command to specify it is not necessary.

**Dots...** – the dots designate, that an element which faces to it, in record of a command it is possible to repeat any number of times.

**The symbol** | – specifies, that it is possible to choose one of two

#### 1.7.3. Operating system WINDOWS Basic catalogues Windows

All catalogues Windows contain in a window fig. 1.7.10. We shall describe some of them.

😋 C: \WIN98		
🛛 Факл Правка Вид Перезод	а. Избранное Справка	19
← · → · 🖬 🐰 🛅 🛱	3 27 × 13 囲・	
Appes CAWIN98		¥
All Users	History     Hovelup	Samples
Applog	Int .	ShelNew
Carloct	🛄 Java	Systickup
Config Content.IE5	Local Settings	System System32
Cookies	Msagent	Taske Contaste
Cursors	NetHood	Temporary Internet Files
📓 Downbaded Piogram Files 🛄 Driviation	Diffine Web Pages	Web
Forts	C PrintHood	Плавнос меню
I History	Recert	П Рабочий стол
•		1
Объектов: 328	70 G MG	🛄 Мой компьютер

1) Command – contains utilities and drivers DOS 7.0, integrated in Windows.

2) System, System32 – contain drivers Windows and libraries.

3) Temp – contains the time files created and used by appendices Windows during work. Names of these files begin with a sign and they have type tmp. Under condition of normal end of work of the appendix and system these files are automatically erased from catalogue Temp. If in work of the appendix or system there was a failure these files can remain in the catalogue. They need to be deleted independently.

4) the Main menu – contains structure of the main menu and labels of the appendices established in system.

5) the Desktop – the global folder, is the uppermost level of system, contains standard folders and appendices, and also the badges created by the user.

6) Fonts – contains a set of the fonts established in system.

- 7) Desktop contains adjustments of the Desktop.
- 8) Cursors contains schemes of indexes of the mouse.
- 9) Media contains sound schemes.
- 10) History magazine of work in Internet.

#### File system Windows

The file system is characterized by the multilevel 32-bit architecture supporting some of file systems. In file system 32 layers from which, now, are used 12 are stipulated. The others are reserved for the further needs. Features of new file system are support of long files names and dynamic cashing at operations of file and network input/output.

Thank you for your attention